edetect_stack

January 12, 2017

Abstract

 EPIC source detection on stacked observations, taken at different epochs and / or in mosaic mode.

1 Instruments/Modes

Instrument	Mode
EPIC MOS:	IMAGING
EPIC PN:	IMAGING

2 Use

pipeline processing	no	
interactive analysis	yes	

3 Description

The meta-task **edetect_stack** performs standardized EPIC source detection on overlapping fields of observations, taken at different epochs or / and in Mosaic Mode. Starting from the filtered event lists, it runs all steps of source detection, produces the necessary input files (images, exposure maps, ...), calls the task **emldetect** for all input images simultaneously, and creates the final stacked source list from its output. Input pointings are considered overlapping if the distance between their centers is **less than 2 \times 12.0 arcmin**.

The handling of **edetect_stack** and its application to a data set are described in Traulsen et al. 2016 (in prep.). For a concise description of the XMM-Newton source detection, you may consult the 2XMM Catalogue User Guide

http://xmmssc-www.star.le.ac.uk/Catalogue/2XMM/UserGuide_xmmcat.html#SrcDet. Details on the individual tasks are given in their respective documentations (linked below).

Standard input to **edetect_stack** are: one attitude file per observation identifier, one ODF summary file per observation identifier, and all event lists, i.e. up to three event lists per OBS_ID keyword. Attitude and summary files are automatically sorted by OBS_ID. In order to use **edetect_stack** with data taken **in mosaic mode** or on observations which have several event lists for one instrument for any reason, **it**




Figure 1: Combining the PSFs of different instruments and observations (offset angles) within the source cut-out radius.

is mandatory to run the task emosaic_prep on the event lists first in order to introduce a pseudo-exposure ID. Otherwise, input files may be confused.

edetect_stack comprises twelve stages, which are run subsequently. The task can be stopped and (re-)started at every stage, provided that all input files to the stage are available. Program flow and input parameters are described in more detail in the following subsections.

3.1 General structure

General structure of **edetect_stack**, starting from event lists, attitude information and ODF summary files:

- sort input files and determine the number of different pointings
- set up the common coordinate system: choose reference coordinates and image size from the pointing coordinates and the position angles of the input files (if not explicitly given by the user)
- check whether all imput pointings are overlapping: If the field of view of an input pointing is not overlapping with any other field by at least 3 arcmin in radius, **edetect_stack** exits with an error. If the full fields of view are overlapping, but a pointing is not overlapping with the user-chosen area of interest (reference coordinates & image size), this pointing is ignored, and a warning ist thrown.
- project the input event lists onto the reference coordinate system
- prepare the input files to source detection per pointing (stages 2-7, see below)
- perform stacked source detection on all pointings simultaneously
- create the final source list, which includes information on the detections in the individual pointings and all-EPIC, and a summary source list, which includes one all-EPIC row per valid detection.

Each input image is combined with its respective background image, exposure map, and detection mask. Within a cut-out radius about each tentative detection, the appropriate PSFs are chosen for all valid images, as illustrated in Fig. 1, and source position, counts, and extent are fit simultaneously.



3.2 Input parameters

The input parameters are organized in three groups: general source-detection parameters of the task **edetect_stack**, parameters determining the program flow, and subtask parameters which are passed by **edetect_stack** to the SAS source-detection tasks when calling them.

The most relevant generic parameters of edetect_stack are

eventsets – a blank-separated list of file names of event lists attitudesets – a blank-separated list of atthkgen attitude files

 ${\tt summarysets} \quad - \quad a \ blank-separated \ list \ of \ {\tt odfingest} \ ODF \ summary \ files$

ecf – (optionally) the list of energy-conversion factors to calculate valid fluxes

pimin, pimax - (optionally) list of lower and upper limits of the energy bands in eV. Will be used for each pointing-in

Page:

3

If all stages of source detection shall be performed, the first three list parameters are mandatory. The event lists should be sorted by observation IDs, i.e. eventsets='pnevents(obs1) m1events(obs1) m2events(obs2) m2events(obs2) pnevents(obs3) ...'. The appropriate attitude and summary files are chosen by edetect_stack according to their observation identifier, i.e. the OBS_ID keywords of the event lists and attitude files and the "Observation identifier" line in the summary file. The file-naming convention of all files will be described in the next subsection.

Parameters which determine the program flow start with "run" (runattcalc, runevselect, ...). Alternatively, the parameters minstage, maxstage can be used to address the program stages by index (indices shown to the left of Figure 2) or by name:

- 1. runattcalc
- 2. runevselectimages
- 3. runeexpmap
- 4. runemask
- 5. runeboxdetectlocal
- 6. runesplinemap
- 7. runeboxdetectmap
- 8. runesensmap
- 9. runemosaic
- 10. runeboxdetectstack
- 11. runemldetect
- 12. finalize

minstage and maxstage have precedence over teh "run..." parameters.

Parameters which are directly passed to another task start with a short version of the parameter name (e.g. att_imagesize, emask_withregionset, emask_regionset). Other parameters which change the behaviour of edetect_stack have a free name format (e.g. pimin, with_att_imagesize).

Default values of the parameters are the values used to produce the 3XMM catalogues where applicable. Part of them differ from the default parameter values of the individual tasks.

4

The energy bands are given as lower limits pimin and upper limits pimax and are the same for all instruments and pointings. Therefore, users need to specify one pimin and pimax component per energy band only, not per image (as in **eboxdetect** and **emldetect**.

The Energy conversion factors (ECFs) are used to convert the EPIC count rates to fluxes and are given via the ecf parameter in units of 10^{11} counts cm² /erg; one ECF per input image, i.e. one value per observation per instrument per energy band. edetect_stack uses

- user-supplied values, if the parameter ecf is set;
- 3XMM conversion factors, if ecf is not set and if standard; energy bands are used
- 0.0 otherwise, which means "NULL" fluxes in the output source list.

A table of all EPIC energy conversion factors is available via the 3XMM-DR5 Catalogue User Guide at http://xmmssc.irap.omp.eu/Catalogue/3XMM-DR5/3XMM-DR5_Catalogue_User_Guide.html#TabNewECFs. The 3XMM conversion factors are only valid if standard patterns are used to produce the images from pipeline event lists. edetect_stack applies the 3XMM patterns by default. More information on ECFs are available via the **emldetect** documentation.

Tasks called by edetect_stack 3.3

edetect_stack consists of twelve subsequent stages during which ten SAS tasks are called to perform the source detection. While running the meta-task, information on the program flow will be shown if SAS_VERBOSITY or the argument of the option '-V' is set to 5 or higher.

Figure 2 illustrates the flow of standard processing: tasks and products, and indicates how often each task is called.

Notes on the individual task calls.

1. attcalc

SAS_ODF is set for each attitude file according to the input parameter summarysets and the observation identifier in the files. The analysis area can be chosen by the user via the parameters att_nominalra, att_nominaldec, and att_imagesize which are forwarded to attcalc and activated by with_att_nominalcoord=yes and / or with_att_imagesize=yes. When automatically determining the image area, "notOnChip" warnings may be sent by esky2det. They can be ignored. edetect_stack informs the user via an extra warning in case an input pointing does not overlap with the chosen analysis area.

2. evselect

By default, EPIC images are filtered with the FLAG and pattern expressions that were used for the 2XMM and 3XMM catalogues (described in the 2XMM Catalogue User Guide). Neither explicit gti filtering nor additional pattern filtering of the input event lists are directly supported by **edetect_stack**. If users want to apply their own filtering expressions, they need to filter the event lists before running edetect_stack and/or create their own input images.

edetect_stack checks whether output images are empty. Instruments / observations for which no image contains any event are ignored in the following.

 $^{^{1}} Cf.\ http://xmmssc-www.star.le.ac.uk/Catalogue/2XMM/UserGuide_xmmcat.html\#ImageCreat/2MM/UserGuide_xmmcat.html$






Figure 2: Structure of **edetect_stack**.

3. eexpmap

Exposure maps are created with withvignetting (see documentation of eexpmap)=no. Vignetted exposure maps are produced in addition, if esp_fitmethod is set to "model (see notes on the call to **esplinemap**).

4. emask

Users are advised to check the automatically created detector masks and to adjust the emask thresholds emask_threshold1, emask_threshold1 if, for example, too large regions are masked.

5. **eboxdetect** (local mode)

Within edetect_stack, eboxdetect is generally called with exposure maps and detection masks, i.e. the parameters withexpimage (see documentation of eboxdetect) and withdetmask (see documentation of eboxdetect) are set to "yes" (eboxdetect default: "no").

6. esplinemap

edetect_stack supports all fit methods of esplinemap, which are explained in the task description (see documentation of esplinemap):

esp_fitmethod=smooth (default of edetect_stack): produce background maps via adaptive smoothing of the cheesed image.

esp_fitmethod=spline: Use a spline fit to produce the background maps. The number of spline nodes is derived from the image size in pixels, per default, as square root of the longest side divided by two. Users can change the number of nodes by changing the value of the parameter esp_nsplinenodes and setting with_esp_nsplinenodes=true.

esp_fitmethod=model: pass vignetted exposure maps to esplinemap via the esplinemap parameter expimageset (see documentation of esplinemap).

If, additionally, esp_withexpimageset2=true: pass unvignetted exposure maps to esplinemap via the esplinemap parameter expimageset2 (see documentation of esplinemap).

Users are advised to check the background maps for fit artefacts like very bright regions and to adjust the fit parameters (esp_nsplinenodes or esp_snrmin, esp_smoothsigma) when indicated.

7. **eboxdetect** (map mode)

The map-mode box source lists per pointing are used as input to the stacked **emldetect** run.

8. esensmap

The creation of sensitivity maps is not mandatory to run the source detection tasks, but recommended for informational purposes. The likelihood threshold mlmin (see documentation of esensmap) of esensmap, for which the upper limit of source counts is calculated, is set to the minimum detection likelihood of edetect_stack (as given via the parameter mlmin), but not below 1.0.

9. emosaic

The energy-resolved mosaic images are created for informational purposes only.

- 10. eboxdetect (stacked, map mode) with emosaic and srcmatch
 - (a) **emosaic** is called to create mosaicked images, background maps, exposure maps, and detection masks of all pointings per instrument and energy band.
 - (b) **eboxdetect** in map mode is run on the *mosaicked* images, i.e. on the same number of input images as in standard source detection, to create a preliminary box source list. Its name derived from the parameter <code>eboxs_boxlistset</code> with an inserted "_intermediate". Within <code>edetect_stack</code>, <code>eboxdetect</code> is generally called with exposure maps and detection masks, i.e. the parameters <code>withexpimage</code> and <code>withdetmask</code> (see documentation of eboxdetect) are set to "yes" (<code>eboxdetect</code> default: "no").
 - (c) **srcmatch** combines the intermediate stacked box source list with the map-mode box source lists of the individual pointings (if created in stage 7). The output source list is named **eboxs_boxlistset**.

The matching radius is determined by **edetect_stack** from the image binning. If users would like to test different matching radii, they may stop **edetect_stack**, adjust the value of the parameter maxerr of **srcmatch** and repeat the matching, before restarting **edetect_stack** with minstage=11 and the adjusted input list.

Please note that all the **eboxdetect** source lists that are produced by **edetect_stack** serve as input to other tasks and are not suitable for a quantitative analysis.

11. emldetect

Within edetect_stack, the emldetect source list is an intermediate product, from which the final stacked source list is created. It is produced with withrawrows (see documentation of emldetect)=yes and, by default, with a lower minimum detection likelihood than the final source list.



3.4 Input / output file names

To ease the handling of the file-name parameters, the task **edetect_stack** uses a fixed structure of file names, composing it of a base name like "image" plus extensions per observation, instrument, and energy band (where applicable). The user can provide base names for each file type, which will be expanded by **edetect_stack** following the pre-defined file-name structure. The default file-name structure is defined as follows:

```
attcalc corrected event lists
                                         events0123456789E000II.fits
evselect images
                                         iimage0123456789E000II_01234_12345.fits
eexpmap un-vignetted exposure maps
                                         expmap0123456789E000II_01234_12345.fits
eexpmap vignetted exposure maps
                                         expvig0123456789E000II_01234_12345.fits
emask detection masks
                                         detmsk0123456789E000II.fits
local-mode eboxdetect source lists
                                         loc1st0123456789E000.fits
esplinemap background maps
                                         bkgmap0123456789E000II_01234_12345.fits
esplinemap cheesed images (diagnostic)
                                         cheese0123456789E000II_01234_12345.fits
map-mode eboxdetect source lists
                                         box1st0123456789E000.fits
esensmap sensitivity maps (diagnostic)
                                         snsmap0123456789E000II_01234_12345.fits
                                         mosaic_EPIC_01234_12345.fits, mosaic_II.fits
emosaic mosaicked images (diagnostic)
```

where the first 10 digits denote the observation ID, "E000" an exposure identifier, "II" the instrument, and the following numbers the lower and upper limits of the energy band in eV respectively. Via the parameter prefix, an additional identifier can be prepended to all file names.

The obvious advantage of the fixed file-name structure is the comprehensive input; its disadvantage the resultant inflexibility regarding input file names. Therefore, lists of file names can be used alternatively to the base names. edetect_stack will sort and associate these input files with different pointings and instruments according to their header keywords OBS_ID, EXP_ID, and INSTRUME. The energy bands, however, cannot be read from the file headers, and standard naming as <first part of the file name>_<PIMIN>_<PIMAX>, using five digits per PIMIN and PIMAX, is mandatory. Example: myinputfile_00500_010000.fits.

The third alternative are ASCII input files, which contain one file name per row. The ASCII file name has to be preceded by an @ sign, as familiar to users from the heatools / FTOOLS tasks. Example: "eventsets=@eventlists.txt",

```
...> cat eventlists.txt
obs1_pn_evts.fits
obs1_m1_evts.fits
obs1_m2_evts.fits
obs2_pn_evts.fits
obs2_m2_evts.fits
```

3.5 Stacked output source list

The final output source list comprises all detections of the intermediate emldetect source list that have an equivalent detection likelihood DET_ML above mlmin in total or in at least one pointing. For each valid detection, it gives one summary line with the combined values of all input observations, one per camera, one per camera and energy band, one all-EPIC summary line per valid pointing and one summary line per instrument per valid pointing. In these summary rows per pointing, the column ID_INST includes the observation ID followed by the usual 0 which marks summary rows. They are calculated by edetect_stack in the same way as the summary rows by emldetect, but they are not necessarily






Figure 3: Sketch of the rows per detection in a stacked source list.

Table 1: Default band assignments of hardness ratios HR_i for the EPIC instruments and default energy intervals during pipeline processing (cf. 3XMM-DR5 Catalogue User Guide http://xmmssc.irap.omp.eu/Catalogue/3XMM-DR5/3XMM-DR5_Catalogue_User_Guide.html#TabBands).

i	n	m	Pipeline energ	gy bands [keV]
1	1	2	0.2 – 0.5	0.5 – 1.0
2	2	3	0.5 – 1.0	1.0 – 2.0
3	3	4	1.0 – 2.0	2.0 – 4.5
4	4	5	2.0 – 4.5	4.5 – 12.0

identical to the results of a separate **emldetect** run on the single pointing. Figure 3 shows a sketch of a stacked source list. A complete list of the table columns is given in Table 2 in Section 8. Since the final stacked source list is created from the intermediate **emldetect** product and detections of low likelihood are rejected, the detection identifiers ML_ID_SRC may have gaps, and the maximum ML_ID_SRC may be larger than the total number of valid detections.

3.6 Usage hints

At **start-up**, the tasks reads several header keywords of the input files in order to establish the stacking parameters and to sort the input files. The I/O performance of the CFITSIO library, which is used to open the FITS files, strongly depends on the file size. Users are recommended to filter the event lists before running **edetect_stack**, if they experience performance issues.

At runtime, the performance strongly depends on the number of images to be processed. The number of pointings, which are combined in one call to **edetect_stack** should be limited to the absolutely necessary. Large mosaics should be split into several regions which are processed separately. Correspondingly, users can divide the field of view of repeatedly observed pointings into smaller areas, process them separately and combine the output source lists.

Pseudo exposure IDs set by emosaic_prep should be below 110100.



3.7 Examples

The most convenient application:

- create a subdirectory where the task is run and all products are stored
- create ASCII lists of the input files
- call edetect_stack and lean back for a while
- check the diagnostic, intermediate, and final data products
- adjust parameters where necessary

Examples for calls to **edetect_stack**:

Process three observations, using default parameters:

Read file names from ASCII files:

Source detections on previously processed files with standard names, re-setting the minimum detection likelihoods:

Interrupt **edetect_stack** after creating the stacked **eboxdetect** source list in order to insert your favourite objects manually or **srcmatch** another list into the input source list of **emldetect**:

Page:

10

4 References

5 Parameters

This section documents the parameters recognized by this task (if any).

Parameter	Mand	Type	Default	Constraints
eventsets	no	filename	event.fits	
		list		

Blank-separated name(s) of input event files, from which images and masks are extracted. Alternatively: name of an ASCII file preceded by '@', containing one file name per line (cf. 3.4).

This parameter is mandatory, if you want to run all stages of the edetect_stack source detection.

attitudesets	no	filename	attitude.fits	
		list		

Blank-separated name(s) of input attitude files, from which the common coordinate system of the stacked observations is derived. One per observation identifier. Alternatively: name of an ASCII file preceded by '@', containing one file name per line (cf. 3.4).

This parameter is mandatory, if you want to run all stages of the edetect_stack source detection.

summarysets	no	filename	summary.fits	
		list		

Blank-separated name(s) of input odf summary files, as provided by **odfingest**. One per observation identifier. Alternatively: name of an ASCII file preceded by '@', containing one file name per line (cf. 3.4).

This parameter is mandatory, if you want to run all stages of the **edetect_stack** source detection.

mlmin			no		float		6.0				[0.0]	: 100.0]		
emldetect:	Minimum	detection	on like	lihood	to b	e reac	ched in	total	or in	at least	one	pointing	to trans	\overline{sfer}

a source from the intermediate to the final output list.

pimin	no	integer	200	500	1000	[0:30000]			
			$2000\ 45$	00					
Lower boundaries of energy bands in source detection. Units: eV									

pimax	no	integer	500	1000	2000	[0:30000]
			4500 13	2000		

Upper boundaries of energy bands in source detection. Units: eV



Page: 11

 ecf
 no
 float
 0.0 0.0 0.0 0.0 0.0 0.0 [0.0 : 1000.0]

Energy conversion factors, given in units of 10^{11} counts cm² / erg, used to derive source fluxes. One value per observation per instrument per energy band. 3XMM values are chosen automatically, if parameter ecf is not set and standard energy bands are used.

 srclistset
 no
 filename
 srclist.fits

Name of output edetect_stack source list

minstage no string 1 [1:12] or stage name

Index or name of stage at which **edetect_stack** should be started. If set, it has priority over the "run*" parameters.

maxstage no string 12 [1:12] or stage name

Index or name of stage at which **edetect_stack** should be stopped. If set, it has priority over the "run*" parameters.

prefix no string

Prefix of all files for which the default name structure is used.

informational no string default | all | none

Write / omit informational output: sensitivity maps, mosaic images (default: yes), cheesed background images and masks, emldetect source images (default: no).

attcalc (stage 1)

runattcalc no boolean true true false

Run task attcalc to establish a common coordinate system. If set to "false", this has to be done manually before starting edetect_stack.

att_eventset no filename events

attcalc: 1. Base name of event lists written by attcalc, expanded by edetect_stack to <att_eventset> <pointing ID><instrument>.fits, or 2. a list of file names, or 3. name of an ASCII file preceded by '@', containing one file name per line (cf. 3.4). Output files, if runattcalc is set to "true" (default), input files to the following tasks otherwise.

with_att_nominalcoord no boolean false true | false

User input of parameters att_nominalra and att_nominaldec. If "false": optimum values are derived by edetect_stack from the attitude files.

 att_nominalra
 no
 angle
 0.0
 [0.0:360.0]

attcalc: Celestial right ascension coordinate of central reference point, if with_att_nominalcoord is set to "true" (default: "false").

att_nominaldecnoangle0.0[-90.0:+90.0]

attcalc: Celestial declination coordinate of central reference point, if with_att_nominalcoord is set to "true" (default: "false").

with_att_imagesize no boolean false true false
User input of parameter att_imagesize. If "false": optimum value is derived by edetect_stack from the attitude files.

attcalc: Image half-size in degrees, if with_att_imagesize is set to "true" (default: "false").



Page:

12

evselect (stage 2) runevselectimages true | false boolean Run task evselect to produce images. If set to "false", the files have to be provided as input. ev_imageset no filename iimage evselect: 1. Base name of image files, expanded by edetect_stack to <ev_imageset><pointing ID> <instrument>_<E_low>_<E_high>.fits, or 2. a list of file names, or 3. name of an ASCII file preceeded by '@', containing one file name per line (cf. 3.4). Output files, if runevselectimages is set to "true" (default), input files to the following tasks otherwise. ev_xcolumn no string column name evselect: Name of column with spatial X coordinates for image creation. ev_ycolumn column name no string γ evselect: Name of column with spatial Y coordinates for image creation. ev_ximagebinsize 80.0 no real >0evselect: Binning factor for the X axis in image creation. ev_vimagebinsize real > 0no evselect: Binning factor for the Y axis in image creation. boolean ev_withxranges false true | false evselect: Use the ev_ximagemin and ev_ximagemax values for the X coordinate ranges for image creation. If true, the parameter ranges are used; if false, the ranges are determined from the data. ev_ximagemin real 1.0 no evselect: If set, the lower limit of the X coordinate for image creation. ev_ximagemax no real 1.0 evselect: If set, the upper limit of the X coordinate for image creation. ev_withyranges no boolean false true | false evselect: Use the ev_yimagemin and ev_yimagemax values for the Y coordinate ranges for image creation. If true, the parameter ranges are used; if false, the ranges are determined from the data. ev_yimagemin real 1.0 evselect: If set, the lower limit of the Y coordinate for image creation. ev_yimagemax real no evselect: If set, the upper limit of the Y coordinate for image creation. ev_withimagedatatype boolean true true | false no evselect: Boolean to choose whether to use the value of the ev_imagedatatype parameter to set the data type of the output image; if the value is false then evselect tries itself to determine the best value for the image data type. Please note: "stand-alone" evselect sets this parameter to "false" by default, edetect_stack to "true".

ev_imagedatatype Int8 | Int16 | Int32 | Real32 | Real64 string Data type to use for the output image. If not set, evselect decides for itself what data type to use. Please note: "stand-alone" evselect sets this parameter to "Real64" by default, edetect_stack to "Int32".

no

Int32

eexpmap (stage 3)

runeexpmap	no	boolean	true	true	false

Run task **eexpmap** to produce exposure maps. If set to "false", the files have to be provided as input.

eexp_expimageset no filename expmap

eexpmap: 1. Base name of *unvignetted* exposure image files, expanded by edetect_stack to <eexp_expimageset> <pointing ID><instrument>_<E_low>_<E_high>.fits, or 2. a list of file names, or 3. name of an ASCII file preceded by '@', containing one file name per line (cf. 3.4). Output files, if runeexpmap is set to "true" (default), input files to the following tasks otherwise.

eexp_attrebinnofloat2.0[0.0:60.0]

eexpmap: Positional accuracy of attitude rebinning in arcseconds. Changes in the attitude less than eexp_attrebin are ignored when rebinning the attitude data. Please note: "stand-alone" eexpmap sets this parameter to 4.0 by default, edetect_stack to 2.0.

emask (stage 4)

runemask	no	boolean	true	true false

Run task emask to produce detection masks. If set to "false", the files have to be provided as input.

emask_detmaskset no filename detmsk

emask: 1. Base name of detection mask files, expanded by edetect_stack to <emask_detmaskset> <pointing ID><instrument>.fits, or 2. a list of file names, or 3. name of an ASCII file preceded by '@', containing one file name per line (cf. 3.4). Output files, if runemask is set to "true" (default), input files to the following tasks otherwise.

emask_threshold1	no	float	0.5	[0.0:1.0]

emask: Threshold parameter 1: fraction of maximum exposure. Please note: "stand-alone" eexpmap sets this parameter to 0.3 by default, edetect_stack to 0.5.

${ m emask_threshold2}$	no	float	1.0	[0.0:10.0]

emask: Threshold parameter 2: threshold for gradient of exposure. Please note: "stand-alone" emask sets this parameter to 0.5 by default, edetect_stack to 1.0.

emask: Read a FITS region file and exclude circular/box regions from the mask.

${f emask_regionset}$	no	filename	emask.fits	

emask: Name of the FITS region file providing the regions to be excluded, if emask_withregionset is set to true.

eboxdetect (local mode)

(stage 5)

${f rune box detect local}$	no	boolean	true	true false	
Run task eboxdetect to produce local-mode input source lists per observation. If set to "false", the files					
have to be provided as input					

1 11 14		0.1	1 1 10	
eboxl_boxlistset	no	filename	eboxlocal.fits	loclst

eboxdetect: 1. Base name of local-mode box list files, expanded by edetect_stack to <ev_imageset> <pointing ID>.fits, or 2. a list of file names, or 3. name of an ASCII file preceded by '@', containing one file name per line (cf. 3.4). Output files, if runeboxdetectlocal is set to "true" (default), input files



Page: 14

to the following tasks otherwise.

eboxl_likemin	no	float	5.0	[1.0:50.0]
eboxdetect: Minimum detec	tion likelihoo	od for includ	ing a source in the output	list. Please note: "stand-

eboxdetect: Minimum detection likelihood for including a source in the output list. *Please note:* "stand-alone" **eboxdetect** sets this parameter to 10.0 by default, **edetect_stack** to 5.0.

$eboxl_boxsize$	no	integer	5	3 5

eboxdetect: Size of detection box (3x3 or 5x5 pixels).

eboxl_nruns no integer 1 [1:4]

eboxdetect: Number of detection runs (detection box size is doubled after each run). Please note: "stand-alone" **eboxdetect** sets this parameter to 3 by default, **edetect_stack** to 1.

esplinemap (stage 6)

 runesplinemap
 no
 boolean
 true
 true | false

 Run task esplinemap to produce spline background maps. If set to "false", the files have to be provided as input.

esp_bkgimageset no filename bkgmap

esplinemap: 1. Base name of background map files, expanded by edetect_stack to <esp_bkgimageset> <pointing ID><instrument>_<E_low>_<E_high>.fits, or 2. a list of file names, or 3. name of an ASCII file preceded by '@', containing one file name per line (cf. 3.4). Output files, if runesplinemap is set to "true" (default), input files to the following tasks otherwise.

$\operatorname{esp_scut}$	no	float	0.002	[0.0:10.0]

esplinemap: Source cut-out flux level in [counts/arcsec²]. Please note: "stand-alone" esplinemap sets this parameter to 0.01 by default, edetect_stack to 0.002.

esp_mlmin	no	float	1.0	[0.0:1000.0]

esplinemap: Minimum single band detection likelihood for sources to be cut out.

${ m esp_fitme}$	ethod	no	string	spline		spline model
1.	D 1	1 C	1 1 C	0	. 1 1	1 11

esplinemap: Background fitting method: spline fit or 2-component background model.

$with_{esp_nspline}$	no	boolean	false	true false
TT · · · · · ·		TC //C 1	11 A . 1 1 C	1 50 1 1

User input of parameter esp_nsplinenodes. If "false": A standard value of one node per 50 pixels is derived by edetect_stack from the image size.

esp_nsplinenodes no integer	13	[10:40]
-----------------------------	----	---------

esplinemap: Number of nodes in spline fit. Please note: "stand-alone" esplinemap sets this parameter to 13.0 by default. edetect_stack uses a default value that depends on image size in pixels.

esp_excesssigma	no	float	4.0	[1.0:6.0]
10 ED1 1 1 1 C		* . 1	1 1 1 1 1	C

esplinemap: Threshold for sigma excesses with respect to background spline fit.

esp_nfitrun	no	integer	4		[1:5]	
1		U				

esplinemap: Number of iterations for removal of excesses. esp_nfitrun=1 means no removal. Please note: "stand-alone" esplinemap sets this parameter to 3 by default, edetect_stack to 4.

$\mathbf{esp_snrmin}$	no	float	30.0	[1.0:1000.0]
esplineman fitmethod smoo	th. Desired	minimum s	ignal to noise ratio during	adaptive smoothing

esp_smoothsigma	no	float	15	[0.0:100.0]



Page: 15

esplinemap, fitmethod smooth: Minimum width of Gaussian smoothing kernel in pixel.

${ m esp_with expimage set 2}$	no	boolean	false	true false			
esplinemap : Use both vigner	esplinemap: Use both vignetted and unvignetted exposure maps for fitmethod=model.						

esp_expimagesetvig filename expvig

esplinemap: 1. Base name of vignetted exposure maps for fitmethod=model, expanded by edetect_stack to <esp_expimagesetvig><pointing ID><instrument>_<E_low>_<E_high>.fits, or 2. a list of file names, or 3. name of an ASCII file preceded by '@', containing one file name per line (cf. 3.4).

 $esp_with cheese image$ boolean true true | false

esplinemap: Optional output of "cheesed" photon images where sources have been masked out. Please note: "stand-alone" esplinemap sets this parameter to "false" by default, edetect_stack to "true".

esp_cheeseimageset no filename cheese esplinemap: 1. Base name of diagnostic output cheesed image files, expanded by edetect_stack to <esp_cheeseimageset><pointing ID><instrument>_<E_low>_<E_high>.fits, or 2. a list of file

names, or 3. name of an ASCII file preceded by '@', containing one file name per line (cf. 3.4).

esp_withcheesemask boolean false true | false no esplinemap: Optional output of a cheese-mask images. Values 0 stand for masked areas, 1 for valid image areas.

 $esp_cheesemaskset$ no filename cheesemask

esplinemap: 1. Base name of diagnostic output cheese mask image files, expanded by edetect_stack to <esp_cheesemaskset><pointing ID><instrument>_<E_low>_<E_high>.fits, or 2. a list of file names, or 3. name of an ASCII file preceded by '@', containing one file name per line (cf. 3.4).

eboxdetect (map mode)

(stage 7)

runeboxdetectmap	no	boolean	true	true	false
Run task eboxdetect to prod	luce map-mo	ode input so	urce lists per observation.	If set	to "false", the files

have to be provided as input.

eboxm_boxlistset filename eboxmocal.fits boxlst no eboxdetect: 1. Base name of map-mode box list files, expanded by edetect_stack to <ev_imageset> <pointing ID>.fits, or 2. a list of file names, or 3. name of an ASCII file preceded by '@', containing one file name per line (cf. 3.4). Output files, if runeboxdetectmap is set to "true" (default), input files to the following tasks otherwise.

eboxm_likemin float 5.0 [1.0:50.0]no

eboxdetect: Minimum detection likelihood for including a source in the output list. Please note: "standalone" eboxdetect sets this parameter to 10.0 by default, edetect_stack to 5.0.

${\bf eboxm_boxsize}$	no	integer	5	3 5
eboxdetect: Size of detection	hox (3x3 c	r 5x5 pixels		

eboxm_nruns	no	integer	3	[1:4]
1 1 4 NT 1 C 1 4	1.	1 4 4 1 1	1 11 1 0	1 \

eboxdetect: Number of detection runs (detection box size is doubled after each run).

eboxm_hrdef	no	integer	1 2 2 3 3 4	[0:10]
-------------	----	---------	-------------	--------

eboxdetect: Array of six integer numbers specifying the upper and lower energy band for each of (up to) three hardness ratios.

esensmap (stage 8)

runesensmap	no	boolean	true	true false
D 1	•, •,			

Run task **esensmap** to produce sensitivity maps.

esen_sensimageset no filename snsmap

esensmap: 1. Base name of sensitivity image files, expanded by edetect_stack to <esen_sensimageset> <pointing ID><instrument>_<E_low>_<E_high>.fits, or 2. a list of file names, or 3. name of an ASCII file preceded by '@', containing one file name per line (cf. 3.4).

emosaic (stage 9)

runemosaic	no	boolean	true	true false
D 1 1 1		C •11		

Run task **emosaic** to produce a mosaic image for illustrative purposes.

${ m emos_mosaicedset}$	no	filename	mosaic	
--------------------------	----	----------	--------	--

emosaic: Base name of illustrative mosaic images, expanded by edetect_stack to <emos_mosaicedset>_EPIC_<E_low>_<E_high>.fits and <emos_mosaicedset>_<instrument>.fits.

eboxdetect (map mode, stacked)

(stage 10)

runeboxdetectstack	no	boolean	true	true false

Run task **eboxdetect** in map mode to produce stacked input source lists. If set to "false", the file has to be provided as input.

	1			
$eboxs_boxlistset$	no	filename	eboxlist.fits	

eboxdetect: Name of stacked box source list. Output file, if runeboxdetectstack is set to "true" (default), input file otherwise.

eboxs_likemin	no	float	5.0	[1.0:50.0]	

eboxdetect: Minimum detection likelihood for including a source in the output list. *Please note: "stand-alone" eboxdetect sets this parameter to 10.0 by default, edetect_stack to 5.0.*

eboxs_boxsize	no	integer	5	3 5
1 1 4 6 6 1 4 4	1 (0.0	F F . 1	\	

eboxdetect: Size of detection box (3x3 or 5x5 pixels).

eboxs_nruns	no	integer	3	[1:4]

eboxdetect: Number of detection runs (detection box size is doubled after each run).

eboxs_hrdef	no	integer	$1\ 2\ 2\ 3\ 3\ 4$	[0:10]

eboxdetect: Array of six integer numbers specifying the upper and lower energy band for each of (up to) three hardness ratios.

emldetect (stage 11)

runemldetect no boolean true true false



eml_scut

XMM-Newton Science Analysis System

Page: 17

eml_mllistset	no	filename	emllist.fits	
emldetect: Name of interm	ediate stacke	ed source lis	t.	
eml_psfmodel	no	string	ellbeta	ellbeta medium slew
emldetect: Model PSF: full	y 2d parame	eterized anal	ytical or medium-accurac	cy EPIC PSFs.
Users are strongly encourage	d to use the	$new\ ellbeta$	PSF for which this task v	vas designed.
eml_mlmin	no	float	0.001	[0.0:100.0]
emldetect: Minimum detec	-] []
note: "stand-alone" emldet to create the intermediate so	ect sets this			
$eml_dmlextmin$	no	float	4.0	[0.0:100.0]
emldetect: Minimum likelil	nood to regar	rd a source a	as extended. Please note:	"stand-alone" emldetec
sets this parameter to 10.0 b	_			
$\mathrm{eml_fitextent}$	no	boolean	true	true false
emldetect: Fit source exter	nt. Please n	ote: "stand-	alone" emldetect sets th	is parameter to "false" b
default, edetect_stack to "t				-
eml_minextent	no	float	1.5	[0.0:300.0]
emldetect: Minimum allow	ed value for	the extent p	parameter of an extent mo	odel in image pixels.
eml_maxextent	no	float	20.0	[0.1:300.0]
emldetect: Maximum allow				1 .
childeteet. Maximum anow	ca varue ioi	one exocut p	parameter of an extent in	odei in image pixeis.
eml_extentmodel	no	string	beta	gaussian beta
emldetect: Model function alone" emldetect sets this p				
eml_nmaxfit	no	integer	1	[1:10]
emldetect: Maximum numb	per of neighbo		es to be fit simultaneously	(eml_nmaxfit*eml_nmuls
≤ 10).	Ü	<u> </u>	v	`
eml_nmulsou	no	integer	1	[1:3]
emldetect: Allow fit to split	up one input	_	aximum nmulsou sources	(eml_nmaxfit*eml_nmuls
\leq 10). Please note: "stand-o	-			`
eml_fitposition	no	boolean	true	true false
emldetect: Fit source posit				
Positive Pos	101101			
${ m eml_determineerrors}$	no	boolean	true	true false
emldetect: Determine stati	stical errors.			
eml_ecut	no	float	15.0	[0.4:100.0]
emldetect: Source cut-out				1 .
fraction of the normalized PS		_		_
in units of image pixels. Pla		-		_
$edetect_stack to 15.0.$		333700 000700	2 par	and the cool of actual

emldetect: Source selection radius for multi-source fitting. Values lower than 1.0: selection radius expressed as fraction of the normalized PSF. Values larger than 1.0 are interpreted as a fixed event cut-out radius given in units of image pixels.

0.9

[0.4:100.0]

float

no



Page: 18

eml_withsourcemap	no	boolean	false	true false
emldetect: Produce simulate	ed source ma	aps.	1	•
		01		
eml_sourceimagesets	no	filename	srcmap	1 1 1 1
emldetect: Base name of our				
edetect_stack to <eml_sour< td=""><td>ceimageset</td><td>><pointin< td=""><td>ig ID><instrument>_<i< td=""><td>L_low>_<l_nign>.lits</l_nign></td></i<></instrument></td></pointin<></td></eml_sour<>	ceimageset	> <pointin< td=""><td>ig ID><instrument>_<i< td=""><td>L_low>_<l_nign>.lits</l_nign></td></i<></instrument></td></pointin<>	ig ID> <instrument>_<i< td=""><td>L_low>_<l_nign>.lits</l_nign></td></i<></instrument>	L_low>_ <l_nign>.lits</l_nign>
$\mathrm{eml_hrpndef}$	no	integer	1 2 2 3 3 4 4 5	[0:10]
emldetect: Array of up to e				. ,
of the hardness ratios for PN;	-			<i></i>
eml_hrm1def	no	integer	1 2 2 3 3 4 4 5	[0:10]
emldetect: Array of up to e	-			wer energy band for each
of the hardness ratios for MO	S1; i.e. two	numbers per	r energy band.	
eml_hrm2def	no	integer	1 2 2 3 3 4 4 5	[0:10]
emldetect: Array of up to e	-			wer energy band for each
of the hardness ratios for MO	S2; i.e. two	numbers per	r energy band.	
eml_withthreshold	no	boolean	true	true false
emldetect: Allow splitting	-			
"stand-alone" emldetect sets	this parame	eter to "falso	e" by default, edetect_st a	ck to "true".
eml_threshold	no	float	10.0	>0.0
emldetect: Value of threshol "stand-alone" emldetect sets				
eml_threshcolumn	no	string	LIKE	LIKE SCTS RATE
emldetect: Column in input	list on which	h eml_thre	shold will be applied, if e	eml_withthreshold is se
to true.				
$eml_withhotpixelfilter$	no	boolean	false	true false
emldetect: If true, the likel			he brightest pixel will be	e ignored (i.e., detections
relying on a single pixel will b	e disregarde	ed).		
$eml_withtwo stage$	no	boolean	true	true false
emldetect: Use two-stage pr	ocess for mu			lease note: "stand-alone"
emldetect sets this parameter				
eml_withxidband	no	boolean	false	true false
emldetect: Write XID band	output for t	he X-ray fol	llow-up and identification	programme.
eml_xidfixed	no	boolean	false	true false
emldetect: Run emldetect	on XID-ban	d image wit	h positions and source ext	tent fixed to input values
eml_xidecf	no	float	0.0	[0.0:1000.0]
emldetect: XID-band energy	conversion		en in units of 10 ¹¹ counts	L J
eml_xidpndef	no	integer	2 3 4	[0:10]
emldetect: Index of the energy	-		l l	
for PN.	/		· ,	

emldetect: Index of the energy band(s) from which the images / start values for the XID band are taken for MOS1.

integer

no

2 3 4

 eml_xidm2def
 no
 integer
 2 3 4
 [0:10]

emldetect: Index of the energy band(s) from which the images / start values for the XID band are taken for MOS2.

Final stacked source list

(stage 12)

finalize	no	boolean	true	true false
----------	----	---------	------	--------------

Calculate the final stacked source list from the intermediate emldetect source list.

6 Errors

This section documents warnings and errors generated by this task (if any). Note that warnings and errors can also be generated in the SAS infrastructure libraries, in which case they would not be documented here. Refer to the index of all errors and warnings available in the HTML version of the SAS documentation.

NotOverlapping (error)

One or more pointings do(es) not overlap with any other input pointing (maximum distance between image centers: 2×12.0 arcmin).

FileMismatch (error)

Number of input event lists does not match number of input attitude files.

ParameterError (error)

Unknown value of a parameter.

ParameterMismatch (error)

Conflict between input parameters (explained in the error message).

ParameterCountMismatch (error)

Number of upper energy-band boundaries does not match number of lower energy-band boundaries.

CIFMissing (error)

Environment variable SAS_CCF is not set.

FileNotFound (error)

Could not open input file. File not found or unreadable.

FileNotCopied (error)

Could not copy the file to the desired location.

KeywordMissing (error)

Mandatory keyword not found in the header of an input file.

EmptySourceList (error)

Input source list to emldetect is empty.

TaskError (error)

Task called by edetect_stack ended in error.

Page: 19

Page: 20

KeywordMismatch (warning)

Header keywords of input files are not consistent. Products of the following tasks may be incorrect.

corrective action: Check input/output files.

KeywordNotChanged (warning)

Header keyword could not be changed.

corrective action: Check order and headers of input files.

ImageNotFound (warning)

An image file that should have been created or input is missing. *corrective action:* Check files and image size / reference coordinates.

InstrumentIgnored (warning)

All images for an instrument are empty in an input pointing.

corrective action: Respective file names are removed from the list of input images

PointingIgnored (warning)

A pointing is not overlapping with the analysis region.

corrective action: No further processing of the corresponding files.

EmptySourceList (warning)

Intermediate eboxdetect source contains no detections.

corrective action: Skipping it.

7 Input Files

Default usage:

- 1. PPS product by task **atthkgen**: ATTHK FITS file containing attitude information (per observation)
- 2. PPS product e.g. by meta-tasks **epchain** / **emchain** or **epproc** / **emproc**: event lists (per observation and instrument)
- 3. PPS product by task **odfingest**: ODF summary file (per observation)

Alternative usage, when running certain stages of edetect_stack:

 PPS products or intermediate products of former calls to edetect_stack: input files for subsequent task stages (per pointing, instrument, and energy band). E.g. images, exposure maps.

8 Output Files

- 1. stacked EPIC edetect_stack source list
- 2. intermediate output of individual tasks called by **edetect_stack** (cf. Subsection 3.3)
- 3. optionally: optional output of individual tasks called by edetect_stack (cf. Subsection 3.3)



Table 2: Columns of the stacked source table

1 2 3	Name ML_ID_SRC BOX_ID_SRC ID_INST ID_BAND	Description unique detection number corresponding eboxdetect input source number instrument ID. 0: all-EPIC, 1: PN, 2: MOS1, 3: MOS2, preceded by the observation identifier in pointing-summary rows. energy band number (0: total)	Unit	Format int. int. int. int.	Stacked
5	ID_CLUSTER	cluster id of detections which have been fit simultaneously		int.	
6	SCTS	background-corrected counts under the entire PSF of the detection	cts	real	total
7	SCTS_ERR	source counts error	cts	real	total
8	$X_{\perp}IMA$	position of the detection in X image direction	image px	real	combined fit
9	X_IMA_ERR	error of X_IMA, corresponding to a 1σ -error in chi-squared statistics	image px	real	combined fit
10	$Y_{-}IMA$	position of the detection in Y image direction	image px	real	combined fit
11	Y_IMA_ERR	error of Y_IMA, corresponding to a 1σ -error in chi-squared statistics	image px	real	combined fit
12	EXT	extent radius of the detection in image pixels, i.e. gaussian sigma or beta model core radius	image px	real	combined fit
13	EXT_ERR	statistical error of the extent	image px	real	combined fit
14	DET_ML	detection likelihood, normalized to two degrees of freedom		real	equiv. likelihood
15	EXT_ML	likelihood of the detection to be extented		real	combined fit
16	BG_MAP	background at the position of the detection	cts/px	real	total
17	EXP_MAP	vignetting corrected exposure of the detection: PSF-weighted mean of the subimages (radius CUTRAD) around the detection	S	real	total
18	FLUX	flux under the entire PSF of the detection	$\rm erg/cm^2/s$	real	weighted sum
19	FLUX_ERR	statistical error of the flux	$\rm erg/cm^2/s$	real	weighted error
20	RATE	count rate under the entire PSF of the detec- tion, corrected for background, vignetting, de- tector efficiency and gaps	cts/s	real	total
21	$RATE_ERR$	statistical error of the count rate	$\mathrm{cts/s}$	real	total
22	RA	right ascension of the detection	degrees	dble.	combined fit
23	DEC	declination of the detectino	degrees	dble.	combined fit
24	RADEC_ERR	combined R.ADec. statistical error $(\sqrt{\sigma_{\alpha}^2 + \sigma_{\delta}^2})$ = $\sqrt{2}\sigma_{1d}$)	arcsec	real	combined fit
25	LII	galactic longitude of the detection	degrees	dble.	combined fit
26	BII	galactic latitude of the detection	degrees	dble.	combined fit
27	RAWX	raw-X coordinate of the detection	px	int.	per image only
28	RAWY	raw-Y coordinate of the detection	px	int.	per image only
29	OFFAX	off-axis angle	arcmin	real	per image only
30	CCDNR	chip number		int.	per image only
31.	, $\mathtt{HR}i$	hardness ratio of count rates:		real	derived from the
33, 35, 37	$(i \in [1, 4])$	$\operatorname{HR}(\operatorname{band}\ m\ ,\ \operatorname{band}\ n) = (\operatorname{rate}(n) - \operatorname{rate}(m))\ /\ (\operatorname{rate}(n) + \operatorname{rate}(m)).$ No energy conversion factors are applied.			total rates



Name 32 , $\text{HR}i_\text{ERR}$ 34 , $(i \in [1, 4])$ 36 , 38		Unit	Format real	$\begin{array}{c} \textbf{Stacked} \\ \text{of } \texttt{HR}i \end{array}$
39 CUTRAD 40 MASKFRAC 41 EEF 42 VIGNETTING	source cut out radius PSF weighted on-chip fraction encircled energy fraction Vignetting as function of off-axis angle and energy; only valid in the intermediate emldetect source list.	image px	real real real real	combined fit max. of minima combined fit NULL
43 ONTIME	Integration time of the CCD, not vignetting corrected. NULL, if CCD no. is not defined (i.e. source center on bad pixels, gaps, damaged CCDs)	s	real	total
44 DIST_NN 45 FLAG	distance to nearest neighbour quality flag placeholder (to be set by dpssflag)	arcsec	real char.	combined fit

9 Algorithm

```
sub edetect_stack {
    # prepare
   read parameters and files
    choose energy conversion factors
   define pointing ids, using header keywords
    check whether pointings are overlapping
   derive reference coordinate system and actual image size
   # SOURCE-DETECTION FILES PER OBSERVATION
    loop over observations
       # set reference coordinate system, if "runattcalc" is set
       set summary file
        copy event files to working directory
        call attcalc per instrument
        # produce images, if "runevselectimages" is set
        define filtering expression
        call evselect per instrument per energy band
        # produce exposure maps, if "runeexpmap" is set
        call eexpmap without vignetting correction per instrument per energy band
        if esplinemap fitmethod is "model"
            call eexpmap with vignetting correction per instrument per energy band
        end if
        # produce detection masks, if "runemask" is set
        choose energy band of exposure image
        call emask per instrument
       # produce local-mode eboxdetect source list, if "runeboxdetectlocal" is set
        determine minimum imagebuffersize from header keywords
```



```
call eboxdetect in local mode
        # produce background maps, if "runesplinemap" is set
        choose fitmethod
        call esplinemap per instrument per energy band
        # produce map-mode eboxdetect source list, if "runeboxdetectstack" is set
        determine minimum imagebuffersize from header keywords if not yet known
        call eboxdetect in map mode
        # produce sensitivity maps, if "runesensmap" is set
        call esensmap per instrument per energy band
        # produce informational mosaic images, if "runemosaic" is set
        call emosaic in different constellations
    end loop over pointing ids
   # STACKED SOURCE DETECTION
   # produce map-mode eboxdetect source list, if "runeboxdetectstack" is set
    create mosaic images per instrument and energy band
    call eboxdetect in map mode on mosaicked input files
   srcmatch the results with the map-mode eboxdetect lists per pointing
   # produce intermediate emldetect source list, if "runemldetect" is set
    determine minimum imagebuffersize from header keywords
    call emldetect
   # create final source list, if "finalize" is set
    sub stack_sourcelist {
        calculate summary lines per pointing and in total
       keep only detections whose detection likelihood is above mlmin
            (in total or in at least one pointing)
       write final fits table
   }
}
```

10 Comments

11 Future developments

References