

Page:

rgslccorr

January 12, 2017

Abstract

RGS light curve correction task

1 Instruments/Modes

Instrument	Mode	
2 Use		
pipeline processing	no	
interactive analysis	yes	

3 Description

rgslccorr is the task that allows the user to create RGS lightcurves. The task corrects the lightcurve from:

- Dead time.
- Background scale.
- Background substraction.

This task needs as mandatory input parameters a RGS event list, the corresponding RGS source list and a timebinsize. It is also possible to create a lightcurve of the two intruments(RGS1+RGS2), if the two events list belong to the same observation and the two instrument exposure were taken simultaneously.

rgslccorr filters the event list file using the source and background region from the source list file and wavelength range or selects a range of CCDs, in case they were enabled. Then, it creates a time serie, corrects for dead time, exposure and backscal. Finally, the source time serie is background subtracted if the user activates the corresponding parameter.

If background subtraction option is enabled, **rgslccorr** task creates an independent background light curve file and also created two columns BACKV and BACKE (background rates and errors) in the background corrected light curve.



XMM-Newton Science Analysis System

Page: 2

Parameters

Energy min value

Energy max value

energymax

This section documents the Parameter	Mand	Type	Default	Constraints
	I	01		
evlist	yes		list	1-2
RGS event file list.				
srclist			list	1-2
RGS source list file.	yes		1180	1-2
timebinsize Size of time bins.	yes	1	real	> 0
outputsrcfilename	no	string		src_rates.ds
ource output file name.				
withbkgsubtraction	no	bool	no	
Enable background subtraction	ction			
outputbkgfilename	no	string	T	bkg_rates.ds
Background output file nar		String		DKg_1ates.us
withfiltering	no	bool	no	
Enable wavelength filtering	g for time ser			(4 1 11 2) (4
filtering Parameter to choose to use	110	string	"wavelength"	"wavelength" "energy
arameter to thoose to use	e enther wave.	length of en	ergy to inter the event ha	
lambdamin	no	real		0
Vavelength min value				
lambdamax	no	real		0
Vavelength max value			1	1
energymin	no	real		0

real

no

0

XMM-Newton Science Analysis System

Page:

3

withccdselection no	bool	no	
---------------------	------	----	--

Enable CCD selection filtering for time serie extraction

ccds	no	int	list	[1:9]
------	----	-----	------	-------

List of CCDs

withtimeranges	no	bool	no	

Use min/max values for time series extraction

timemin no	time		
------------	------	--	--

Start time for time series

. •			
timemax	no	time	

Stop time for time series

orders	no	list	1 2	1-2

RGS orders to be used in the selection expression

sourceid	no	int	1	

Source identifier that appears in the source list file.

5 Errors

This section documents warnings and errors generated by this task (if any). Note that warnings and errors can also be generated in the SAS infrastructure libraries, in which case they would not be documented here. Refer to the index of all errors and warnings available in the HTML version of the SAS documentation.

BinsizeVal (error)

The value of the bin size must be an integer.

WrongInputFiles (error)

The number of RGS event files and RGS source list must be the same.

EventListSize (error)

The number of RGS event files must be one or two.

WrongObservation (error)

It is not possible to create a lightcurve of two event files from different observations.

NotOverlappingTime (error)

The two RGS event list do not overlap in time.

BinningError (error)

Error calculating the number of bins. Check the start time and stop time.

NoFilteredEvents (warning)

One of the CCD does not have any event. corrective action:

6 Input Files

- 1. RGS event list file.
- 2. RGS source list file.

7 Output Files

1. Lightcurve file.

8 Algorithm

9 Comments

•

References